



SCV 备份随机失败,并显示:"仅允许在 Read\_Write (RW) 卷上进行操作"

https://kb-cn.netapp.com/data-mgmt/SnapCenter/SC\_KBs/SCV\_Backup\_randomly\_fails\_with\_\_Operati...

Updated: 周三, 09 7月 2025 16:47:09 GMT

## 适用场景

- 适用于VMware vSphere的SnapCenter插件(SCV) 4.x
- 数据保护源 SVM 和目标 SVM 具有重复的数据 LIF IP 地址(VServer-DR/SVM-DR)
- 数据存储区与 SMBC (SnapMirror 业务连续性) 一起使用

## 问题描述

- SCV 备份随机失败,因为它尝试连接目标 SVM 而不是源 SVM 来拍摄快照
- SCV 慢跑日志显示错误:

[ERR] Failed to run a command New-NcSnapshotMulti

'NetApp provides no representations or warranties regarding the accuracy or reliability or serviceability of any information or recommendations provided in this publication or with respect to any results that may be obtained by the use of the information or observance of any recommendations provided herein. The information in this document is distributed AS IS and the use of this information or the implementation of any recommendations or techniques herein is a customers responsibility and depends on the customers ability to evaluate and integrate them into the customers operational environment. This document and the information contained herein may be used solely in connection with the NetApp products discussed in this document.'

[DBG] ex.Message : Invalid input. Reason: Operation allowed only on
Read\_Write (RW) volumes.
[DBG] ex.InnerException.Message : Invalid input. Reason: Operation allowed
only on Read Write (RW) volumes.

• vmcontrol.log 表示在发生错误之前,NFS LIF 发现了与平常不同的 SVM

DEBUG <SCV> --- [359023572-29370] c.n.a.m.DatastoreStorageDetailsCache
: Storage footprint found for nfsLif <NFS\_LIF> and exportPath
<EXPORTPATH>: ipAddress null vserverName <SVM> volumeName <VOLUMENAME>
junctionPath <JUNCTIONPATH> isLocatedOnFGfalse