

## @mindtouch"

## 由于NAT服务转换IP地址、挂载操作失败、权限被拒绝

https://kb-cn.netapp.com/on-prem/ontap/da/NAS/NAS-KBs/Mount\_operation\_fails\_with\_permission\_de... Updated: 周五, 117月 2025 11:43:02 GMT

## 适用场景

- ONTAP 9
- NFS
- 网络地址转换(Network Address Translation、NAT)服务。

## 问题描述

• 尽管存储和客户端上的权限设置正确、挂载操作仍会失败、并显示"permission denied"

```
[root@linux1 ~]# mount -t nfs -o vers=3,tcp 10.20.30.40:/vol -vvv
mount.nfs: timeout set for Mon Dec 7 16:28:48 2020
mount.nfs: trying text-based options 'vers=3,tcp,addr=10.20.30.40'
mount.nfs: prog 100003, trying vers=3, prot=6
```

'NetApp provides no representations or warranties regarding the accuracy or reliability or serviceability of any information or recommendations provided in this publication or with respect to any results that may be obtained by the use of the information or observance of any recommendations provided herein. The information in this document is distributed AS IS and the use of this information or the implementation of any recommendations or techniques herein is a customers responsibility and depends on the customers ability to evaluate and integrate them into the customers operational environment. This document and the information contained herein may be used solely in connection with the NetApp products discussed in this document.'

1

```
mount.nfs: trying 10.20.30.40 prog 100003 vers 3 prot TCP port 2049
mount.nfs: prog 100005, trying vers=3, prot=6
mount.nfs: trying 10.20.30.40 prog 100005 vers 3 prot TCP port 635
mount.nfs: mount(2): Permission denied
mount.nfs: access denied by server while mounting 10.20.30.40:/vol
```

```
• 环境中使用NAT服务来屏蔽客户端IP地址。
```

© 2023 NetApp. No part of this document covered by copyright may be reproduced in any form or by any means—graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system—without prior written permission of the copyright owner. For more information, see Legal Notices.